

MPX Launcher / USB Dongle für Windows 11

für MPX # 85149
(schwarzer / blauer USB-Stecker)

1. Download

Die neuesten Treiber mit Signatur für Windows 10/11 finden Sie hier :

<https://www.silabs.com/software-and-tools/usb-to-uart-bridge-vcp-drivers?tab=downloads>

Laden Sie nur diese zip-Datei in Ihren lokalen Downloadordner herunter :

Software · 11

CP210x Universal Windows Driver

v11.5.0
12/31/2025

2. Treiberinstallation

Da moderne Versionen der Treiber keine automatische Ausführungsdatei (.exe) mehr besitzen, erfolgt die Installation wie folgt:

1. Öffnen Sie den entpackten Ordner.
2. Suchen Sie die Datei `silabser.inf`.
3. Machen Sie einen Rechtsklick auf die Datei und wählen Sie **Installieren** (oder *Weitere Optionen anzeigen > Installieren* in Windows 11).

3. Gerät zuweisen

1. Schließen Sie Ihr CP210x-Gerät (z.B. MPX USB Dongle) an einen USB-Port an.
2. Öffnen Sie den **Geräte-Manager** (Rechtsklick auf Start > Geräte-Manager).
3. Suchen Sie unter **Anschlüsse (COM & LPT)** oder **Andere Geräte** nach Ihrem USB-Gerät.
4. Machen Sie einen Rechtsklick darauf, wählen Sie **Treiber aktualisieren** und wählen Sie die Option *Auf meinem Computer nach Treibern suchen*.
Wichtig : Verweisen Sie manuell auf den Ordner, den Sie zuvor entpackt haben. Lassen Sie Windows nicht automatisch suchen, da Sie sonst wieder den alten Treiber installieren !!

English >>> see next page !

MPX Launcher / USB Dongle for Windows 11

for MPX # 85149
(black / blue USB-Plug)

1. Download

You can find the latest signed drivers for Windows 10/11 here:

<https://www.silabs.com/software-and-tools/usb-to-uart-bridge-vcp-drivers?tab=downloads>

Download only this zip file to your local download folder:

Software · 11

CP210x Universal Windows Driver

v11.5.0
12/31/2025

2. Driver installation

Since modern versions of the drivers no longer include an automatic executable file (.exe), installation is performed as follows:

1. Open the extracted folder.
2. Locate the file silabser.inf.
3. Right-click the file and select Install (or Show more options > Install in Windows 11).

3. Assigning the device

1. Connect your CP210x device (e.g., MPX USB dongle) to a USB port.
2. Open Device Manager (right-click **Start** > **Device Manager**).
3. Look for your USB device under **Ports (COM & LPT)** or **Other devices**.
4. Right-click it, select **Update driver**, and choose the option **Browse my computer for drivers**. **Important:** Manually point to the folder you extracted earlier. Do not let Windows search automatically, otherwise you will end up installing the old driver again!!